

Reptilase Time with reflex to Reptilase Time 1:1 Mix

Order Name: **REPTILASE TIME**
 Test Number: 6905511
 Revision Date: 12/10/2022

| TEST NAME | METHODOLOGY | LOINC CODE |
|--|---|------------|
| Reptilase Time with reflex to Reptilase Time 1:1 Mix | Electromagnetic Mechanical Clot Detection | |

SPECIMEN REQUIREMENTS

| | | | | |
|--------------|---|---------------|--------------------------------|-----------------------|
| Specimen | Specimen Volume (min) | Specimen Type | Specimen Container | Transport Environment |
| Preferred | 1 mL | Plasma | Sodium Citrate 3.2% (Blue Top) | Frozen |
| Instructions | <p>Specimen Type: Blue-top (sodium citrate) tube</p> <p>Specimen Storage: FREEZE</p> <p>Specimen Collection: CITRATED PLASMA SAMPLES SHOULD BE COLLECTED BY DOUBLE CENTRIFUGATION. Blood should be collected in a blue-top tube containing 3.2% buffered sodium citrate.[1] Evacuated collection tubes must be filled to completion to ensure a proper blood to anticoagulant ratio.[2,3] The sample should be mixed immediately by gentle inversion at least six times to ensure adequate mixing of the anti-coagulant with the blood. A discard tube is not required prior to collection of coagulation samples except when using a winged blood collection device (i.e. 'butterfly'), in which case a discard tube should be used.[4,5] When noncitrate tubes are collected for other tests, collect sterile and nonadditive (red-top) tubes prior to citrate (blue-top) tubes. Any tube containing an alternate anticoagulant should be collected after the blue- top tube. Gel-barrier tubes and serum tubes with clot initiators should also be collected after the citrate tubes. Centrifuge for 10 minutes and carefully remove 2/3 of the plasma using a plastic transfer pipette, being careful not to disturb the cells. Deliver to a plastic transport tube, cap, and recentrifuge for 10 minutes. Use a second plastic pipette to remove plasma, staying clear of the platelets at the bottom of the tube. Transfer the plasma into a LabCorp PP transpak frozen purple tube with screw cap (LabCorp 49482). FREEZE immediately and maintain frozen until tested. Please print and use the Volume Guide for Coagulation Testing to ensure proper draw volume. Please print and use the Volume Guide for Coagulation Testing to ensure proper draw volume.</p> <p>Specimen Stability: Ambient: Not Available, Refrigerated : Not Available, Frozen: Not Available</p> | | | |

GENERAL INFORMATION

| | |
|---------------------|--|
| Expected TAT | 2 - 3 days |
| Notes | Labcorp Test Code: 117180 |
| CPT Code(s) | 85635 |
| Service Provided By |  labcorp Oklahoma, Inc. |